

HORUS 3D SCANNING FOR EVERYONE

GUIDE TO POST-PROCESSING OF THE POINT CLOUD



Contents

- 3 Reconstructing the point cloud with MeshLab
- **16** Reconstructing the point cloud with CloudCompare

HORUS

1 Reconstructing the point cloud with MeshLab

Introduction to MeshLab¹

MeshLab is an advanced 3D mesh processing software system which is commonly used in the most technical fields of 3D development and data handling. MeshLab is open source software which is freely available under GNU (GPL) licence. It is used as a complete program and also as a library for other software programs.

MeshLab was developed by the ISTI-CNR investigation centre; MeshLab was initially created as course work at the University of Pisa at the end of 2005. The system is designed to transform typically unstructured 3D models arising from 3D digitalisation of pipelines. MeshLab is designed for managing and processing large unstructured meshes. It comes with a set of tools for editing, cleaning, repairing, inspecting, rendering and converting this type of mesh.

The automatic mesh cleaning filters include: the removal of duplicated, unreferenced vertices, non manifold edges and null faces. Remeshing tools based on quadric error measure, subdivision surfaces and surface reconstruction algorithms from point clouds based on the ball-pivoting technique and on the Poisson surface reconstruction approach. For noise removal, MeshLab offers various filters to smooth out noise, as well as tools for curve analysis and visualisation.

Includes a range map alignment tool based on the iterative closest point algorithm. MeshLab also includes an interactive mesh painting system allowing areas to be highlighted and any effects of noise to be smoothed out.


MeshLab is available for the majority of operating systems including Windows, Linux, Mac OS X, with reduced functionality for iOS and Android. The system is compatible with the following formats for both input and output: PLY, STL, OFF, OBJ, 3DS, VRML 2.0, U3D, X3D and COLLADA.

MeshLab also allows point clouds reconstructed using Photosynth to be imported.


Opening PLY files in MeshLab

Open the point cloud in MeshLab. The point cloud will have the ".ply" extension.

Opening MeshLab: you will see a menu at the top the main window of the program, and a tool bar underneath it, and finally, a 3D viewfinder that occupies the majority of the window.



Importing a Mesh file: File > Import Mesh.



Selecting the points model (.ply): go to *Import Mesh*, select the point cloud file that you want to import and then click on *Open*.


The Horus scanning software saves the point clouds as ".ply" files by default.

Co Import Mesh			
😂 💿 - 📜 🖷 Decurs	entos 🔸 Escaneos 🕨 Pruebas nuevas	Bustar Picebas nuevas	
Organizar • Naeva	corpeta	⊨ • 3 0	
A Favoritos	Biblioteca Documentos Poetas nuevas	Organizar por: Caspeta =	
E Escritorio	Norder	Fecha de modifica-	
Stics reciertes	BelsLely	18/02/2013 15/02 Archive PLV	
Thisteen	BolsZpty	18/02/2013 15/07 Archivo PCY	
Recurrentes	Coleralphy	17/02/2015 15-27 Archivo PCY	
E Imágenes	Colour 2 ply	17/92/2013 15/32 Archive PCY	
J Misica	Colora Jply	17/92/2013 15:43 Andrivo PCY	
Wideos	Cabeza4.phy	17/02/2015 15:47 Archivo PCY	
	Caters 5 ply	17/02/2013 3914 Archivo PEY	
A lavies	🔓 cabeza	17/02/2013 18/07 Lista de cetificad	
10.0444	Casal.ply	18/02/2013 34:53 Archivo PEY	
Sind -	*(`****		
Nor	ribue	All known formats (1 plv 1 sti 1.	
		Abria V Cancelar	
		104 CACHA	

Viewing the point cloud: once the file has been imported, a 3D visualisation of that cloud will appear in the space.

If the point cloud was generated from a texture scan, the point cloud will reflect the colours of the scanning.


If it was generated from a simple scan without texture, all points will be displayed in the colour selected at the time of scanning.



Cleaning the point cloud

The point cloud could contain imperfections and noise, or simply points that you do not want to be part of the final model. MeshLab enables you to select points of the cloud and delete them.


Select Vertexes tool: click on the *Select Vertexes icon* on the tool bar which enables you to select points in a three-dimensional space using a two-dimensional rectangle shape.




Selecting the vertexes: you can add more points to the selection by holding down the *Control* key while moving the left button of the mouse. The "+" symbol will appear next to the cursor.

You can also deselect points that you have previously selected by holding down the *Shift* key while moving the left button of the mouse. The "-" symbol will appear next to the cursor. You can select the vertexes by holding down the left button of the mouse and moving the cursor over the screen. The vertexes selected will be shown in red.


Once you have selected the vertexes that you want to delete, release the left button of the mouse.



Deleting unwanted vertexes: once you have selected the vertexes that you want to delete, click on the **Delete Selected Vertex** icon located on the tool bar.




Clean point cloud: it is important that the point cloud to be reconstructed is largely free from noise. The reconstruction algorithm partly filters the noise, but it if the cloud has many points that do not belong to the model, the results of the reconstruction will not be accurate.



Processing the point cloud

In order to process a point cloud you will need to create the object normals:


Compute normals menu: Filters > Normals, Curvatures and Orientation > Compute normals for point sets).



Compute normals window: in this window you will need to change the **Neighbour number**, which reflects the number of close points needed to compute the normal.

The recommended initial values are 10, 50 or 100. You might need to adjust this value later. It is advisable to keep the defaults for all other values.


Once you have made the adjustment, click on the **Apply** button. The program will take a few seconds to compute the normals. Once it has finished click on the **Close** button.



Showing the normals: the best reconstructions are generally achieved when the direction of the normals is facing away from the object.

To display the normals, go to *Render > Show Normal/Curvature*.


To hide them, go back to the same tab and click again to deselect.



Viewing the normals: the normals will appear as blue lines over the surface of the point cloud.

It could occur that some normals are not facing away from the exterior of the object. The geometry, the cloud density, and the neighbour number at the time of computing the normals will affect the result.

In the event of some of the normals not facing away from the exterior of the object, it is advisable to recompute the normals by varying the neighbour number until valid results are achieved.



Reconstructing the object from the point cloud

Using the normals generated in the previous section, you can proceed to reconstruct the object.

Reconstruction filter menu: Filters > Remeshing, Simplification and Reconstruction > Surface Reconstruction: Poisson.

di Meshuki (Akit v1.14073 - Project,4)	Roha Complex/Shape Zapering	
B File Edit Fitters Render View Windows Tools Help	CSG Operation	
An of the Composition of the second sec	Cit Operation Cit Operation Control to Automation Control to Control to Control Control to Control Control to Control Co	
1704 66 1792 - 483	Stabilitie Scheiden Uitige Stabilitie Scheiden Uitige Stabilitie Scheiden Magen en Stabilitie Scheiden Scheiden en Scheide Restruction Station Statige Scheiden Scheiden Scheiden Scheiden Statige Scheiden Scheiden Scheiden Scheiden Scheide Restruction Scheiden Scheiden Scheiden Scheider Bescheiden Scheiden Scheiden Scheiden Scheider Mehranden Scheiden Scheiden Scheiden Scheider Mehranden Scheiden Scheiden Scheiden Scheider Mehranden Scheider Scheider Scheider Scheider Scheider Mehranden Scheider Scheider Scheider Scheider Scheider Mehranden Scheider Scheider Scheider Scheider Scheider Mehranden Scheider Scheider Scheider Scheider Scheider Scheider Mehranden Scheider Sche	

Reconstruction filter window: in this window you can modify the Octree Depth and Solver Divide values.

The recommended initial values are between 6 and 12 (if your computer is not very powerful the maximum recommended value is 11). It is advisable to keep the defaults for all other values.

As these variables are increased, the accuracy of the final model will also increase, however, the processing time will also be longer.

Once you have made the adjustment, click on the *Apply* button. The processing time can vary from a few seconds to several minutes. The "Not responding" window could appear during this time. Unless a pop-up window appears, do not close the window. The processing time depends on the specifications of the computer which is running the program. It is not advisable to use a low spec computer for processing point clouds.


Once the reconstruction process has finished, click on the *Close* button.



Viewing the results of the reconstruction


Once the reconstruction is finished, the layers of the point cloud and the reconstructed object will be overlapping. To only view the reconstructions results, simply hide the point cloud layer.

Layer visualisation window: to show the layer visualisation window, click on View > Show Layer Dialog.




Hiding the point cloud layer: the eye icon that appears on the left of the name of each layer can be used to view each layer. Click on it to show or hide the layers.

The layer containing the point cloud will be hidden to improve the visualisation of the reconstruction.




Saving the results of the reconstruction

Export Mesh menu: this option is located under File > Export Mesh.



Export window: select the Export Mesh As option to export a file in the STL format, select the location where you want to save it, then click on the *Save* button.


You should choose the STL format because all the slicing software programs used in 3D printing can open it correctly. If you want to export the file for other uses, you can select a different format.



Merging point clouds with MeshLab


The point cloud may sometimes be incomplete, due to the geometry of the scanned object or the number of lasers used during the scanning process. The solution is to scan the object again by placing it in different position on the platform or by using another laser. Then merge the two point clouds together. To explain how this method works, we have used two point clouds, however, this process can be carried out with as many point clouds as you like - the procedure remains the same.

Open the ".ply" files of the point clouds from the two scanning processes.



In the layer visualisation window (CTRL + L), select a layer and compute the normals. Once the process is finished, do the same with the other layer. Check that the graphic form (by viewing the normals of each layer) has been calculated correctly.

Align tool: to access the alignment tool, go to Edit > Align.




GUIDE TO POST-PROCESSING OF THE POINT CLOUD HORUS

Reconstructing the point cloud with MeshLab


Alignment panel: click on the first layer in the Align tool panel and then on the Glue Here Mesh button. This action will fix the first point cloud in the space.

Then select the second layer and press on the Point Based Glueing button and a new window will open.



This window enables you to position the point clouds so that it is easier to align the points. Then select at least four matching pairs of points on each of the point clouds. To select a point, simply double-click the mouse over the point cloud.


The points selected will be indicated numerically to prevent errors from occurring. If a point is not valid, you will need to click on *Cancel* and open the window again as there is no option to Undo.




Once you have selected the matching points on both clouds, click on **OK**.

Following the previous step, check that the point clouds have been aligned. If not, repeat the previous step until they are correctly aligned.

To complete the alignment click on Process.



Visualisation of the aligned point clouds: you can check the results of the alignment simply by looking at it, the details improve and the missing points are corrected.




Merging point clouds

The point clouds aligned at the previous step are not joined, meaning that they are two separate point clouds.

You will need to merge them together in order to reconstruct the object.


Merging layers menu

Merging visible layers: to access the tool for merging visible layers, go to the Filters menu: Filters > Mesh Layer > Flatten Visible Layers.



Merging visible layers menu: in this window the select the Keep unreferenced vertices option.

Then click on **Apply**



HORUS

Reconstructing the point cloud with MeshLab

The result of merging the point clouds is a new point cloud with a better resolution.


Once the layers have been joined, recompute the normals of the new point cloud. To obtain the reconstructed model, as was previously explained.

Smoothing out the reconstruction results


When objects are reconstructed from a point cloud, the result might not be not totally accurate. The missing points affect the reconstruction and the lack of points cannot always be resolved by merging various point clouds together.

An example of such an object could be the object shown earlier; the base of the object cannot be scanned (as it is supported by the base) and the top part has no points due to the geometry.


However, the reconstruction algorithm will always attempt to close the faces in order to achieve a closed surface.




Top part before reconstruction










Top part after reconstruction

Bottom part after reconstruction

As you can see, the reconstruction process has closed the top and bottom parts, but there is still room for improvement.

To improve the results, you can apply smoothing filters to any areas which have been poorly reconstructed.

Face selection tool: this tool works in the same way as *Select Vertexes*, the sole difference is that it selects faces instead.




Selecting inaccurate faces: as with the other tool, right-click the mouse and move the cursor to select the faces that you want to smooth out.


It is important to remember that as well as selecting the visible faces, you will also need to select the ones in the rectangular box, which are not visible from this perspective.

To deselect faces that you have selected but do not want to modify, left-click on *Select Faces* in a rectangular region on the tool bar again. The position of the object will change, click on the face selection tool again. During this process the faces that were selected previously remain selected. Finally, press the Shift key while moving the cursor over the faces that you do not want to modify.

Once you have made sure that only the faces to be smoothed out are selected, click on *Select Faces* in a rectangular region. The faces remain selected.



Smoothing filter menu: the *Taubin Smooth* filter is applied to the selected faces, which is accessed via *Filters > Smoothing, Fairing and Deformation > Taubin Smooth*.




Taubin Smooth filter: in the Taubin Smooth window, various parameters can be adjusted.

It is recommended to enable *Preview* by the ticking box so that the effects of adjusting the parameters on the object can be viewed in real time.


It is also recommended to keep the default *Lamda* value. In the example Mu and *Smoothing Steps* have been modified.

The parameters will be different depending on the error of the faces created during reproduction, so it is advisable to try different values until you achieve the correct result.


After you have adjusted the parameters to the desired values, click on the **Apply** button.



The result of applying the smoothing filter is significant. Applying the smoothing filter to all faces reduces the detail of the object, so it is important to only apply it to the inaccurate faces.



Top part after applying the smoothing filter



Bottom part after applying the smoothing filter

2 Reconstructing the point cloud with CloudCompare

Introduction to CloudCompare²

CloudCompare is a program for processing point clouds (such as those obtained using a 3D scanner). It also processes triangular meshes and calibrated images.

This software was created during a collaboration between Telecom ParisTech and the R&D division of EDF. The CloudCompare project was launched in 2003 with the doctoral thesis of Daniel Girardeau-Montaut on Detection of Changes in 3D Geometric Data. At that time, his main aim was to rapidly detect changes in high density point clouds generated by laser scanners in industrial facilities (such as power stations) or on construction sites. It later evolved into a more general and advanced 3D data processing software program. It is now is an independent and freely available open source software.


CloudCompare provides a basic set of tools for editing and rendering point clouds and triangular meshes. It also offers various advanced processing algorithms to perform tasks such as: projections, records, distance calculations, statistics, segmentation or estimation of geometric characteristics.

CloudCompare is available on Windows, Linux and Mac OS X, for both 32-bit and 64-bit architectures. It is developed in C ++ with Qt.

Opening PLY files in CloudCompare

Open the point cloud with the ".ply" extension In CloudCompare.

Opening CloudCompare: you will see a menu at the top the main window of the program and a tool bar underneath it on the right, a console at the top and finally, the 3D viewfinder.



Importing a Mesh file: go to File > Open.

											(leud	lomp	are vi	2.6.0	64 bit	s] - [3	D Vie	w 1]								×
	e Edit 1 Open		Display	Plugins 4 X							b.7	55		1.~	4		1.		÷.,	 0	 +	: 0	 124		Remo	we filter	- 15
	Sare Primitive fa		Ctrl+5		6		,1			<u>^</u>			ľ					- 1.3m					 5285				
	3D mouse	,	>																								
	Close all																										
L -	Quit																										
+-																											
م 1				Camera I	Link																						
ø	Properties				e																						
60 (#																											
0 0																											
<u>an</u>																											
	Console					-																		250			81
1	[16:03:5 [16:03:5							SUCCES	isfully																		
	[16:03:5																										
Open																											

Selecting the points model (.ply): from the *Open* window, select the point cloud file that you want to process. Once you have select the file, click on *Open*.

The Horus scanning software saves the point clouds as ".ply" files by default. You will need to select this file type from the drop-down menu.

		[64 bits] - [3D View 1]
File Frit Tool	Diselaw Planins 3D Vews Heln Open	s file(s)
< Sange	im BDesktop Scans	
< ange	in a bestop scars	
laces	Name	Size Modified
	Totem.phy	11.4 MB 16:58
Recently Used	🖹 Bola.ply	6.8 MB 18/02/15
angettm		
Desktop		
FRe System		
1131071700A		
DATA		
Documents		
Music		
Pictures		
Videos		
Downloads		
		PLY mesh
		Cancel Op
		Cancel Op

Properties of ".ply" files: this window displaying advanced configuration options will appear when a ".ply" file is opened. It is recommended to keep the default values. To continue to open the file, click on *Apply*.

Type PLY_LITTLE_E	NDIAN	
Elements 1	Properties 6	
Point X	vertex - x [PLY_FLOAT]	Y
Point Y	vertex - y [PLY_FLOAT]	\
Point Z	vertex - z [PLY_FLOAT]	~
Red	vertex - red [PLY_UCHAR]	V
Green	vertex - green [PLY_UCHAR]	~
Blue	vertex - blue [PLY_UCHAR]	~
Intensity	None	~
Nx	None	×
Ny	None	Y
Nz	None	V
Faces	None	V
Texture coordinates	None	~
Scalar	None	~
Add Scalar field		

GUIDE TO POST-PROCESSING OF THE POINT CLOUD


HORUS

Reconstructing the point cloud with CloudCompare

Viewing the point cloud: once the point cloud has been imported, you will be able to see view it in the 3D viewfinder window.

If the point cloud was generated from a texture scan, you will see the point cloud in the colours of the scanning.

If it was generated from a simple scan without texture, all points will be displayed in the colour selected at the time of scanning.




Cleaning the point cloud

The point cloud could contain imperfections and noise, or simply points that you do not want to be part of the final model. CloudCompare enables you to select points of the cloud and delete them.

Segmentation tool: the first step for cleaning the point cloud is to select the layer than contains it. Click on the layer named Cloud in the file tree on the the left side.

The click on the Segment icon on the tool bar.

This tool enables you to select points in a three-dimensional space using a two-dimensional polygon or a rectangle. How? Think of this tool as a box for modifying one of the faces, which selects all of the points within it from front to back.



Pause and position: occasionally, the points to be eliminated might not be visible from the initial view. The Segment tool consists of various actions which include: **Pause**, **Selection**, **Segment In**, **Segment Out**, **Clear segmentation**, **Confirm segmentation**, **Confirm and delete hidden points** and **Cancel**.

The *Pause* button enables you to move freely across the point cloud without selecting any points. Once the cloud is in the desired position, click on *Pause* again to start selecting points.


						Clos	dComp	are v2.6.0	0 (64 bit	ts] - [3	D View	1]								
	Edit Tools																			88
															 1.00		1.714			- 15
ν		$\otimes \mathbb{D} \mathbb{X} $	0 11	1 12 1	8 X 3	C 162 S	6 5	1.5.	9 W	16	21	12 T	0	8 1	 2	UN	637 ·	Ret	nove filter	- P
	DB Tree		8								Segner	ation (DA				0			9 1	8 8
~	🗆 🕅 🍓 Toter	.pty (/home/angell.										to segme								
-	🖬 🖨 Tel	em - Cloud																		
ы											<	سل								
+																				
Τ.											1									
L. ~		Camera Li	sk –								388									
÷-	Properties										1	-								
q			÷.								10.0									
	Property	State/Value	. I I I								100		14 - L							
1	CC Object	Totem - Cloud	1.1									1996	14							
1	Name Visible	Totem - Cloud	ч.								Terrar a		8							
6	Show name (in									\setminus		17								
	Colors	RGB V									-		Δ.							
		X 132.144	1									-	10 I							
1	Box dimensions										224	5								
10		Z: 199.099							\leq											
-	Box center	X: 5.53957 Y: -21.4695																		
0			- L															100		
-	Console																			13
-	[17:05:22] [PLY	Element 'face' war	ignored	las it has	instancel															
	[17:05:24] [UO]	File '/home/angell/	N/Deskt	op/Scans/I	otem.pty'i	oaded succe	issfully													
	[17:05:24] [VB0	VBO(s) (rejinitial	zed for	cloud 'Tota	m - Cloud	(10.88 Mb	= 100.	00% of po	ints coul	id be lo	aded)									

Segment Out: the *Selection* option enables you to select the points using a polygon with the vertexes marked or using the rectangle.


To use the *Polygonal selection*, left-click the mouse where you want the first vertex to be located, then click again where you want the second vertex to be located, and so on. Once you have defined the polygonal selection, right-click the mouse. Then click on one of the segmentation options.

There are two segmentation options: Segment In or Segment Out.

With the *Segment Out* option, the points outside of the selection polygon remain visible, whereas those within it are moved to another hidden layer.




Segment In: in contrast, with the *Segment In* option, the points within the selection polygon remain visible and those outside of it are moved to another hidden layer.




Cleaning the point clouds: the unwanted points will no longer appear after segmentation.

There are two options for completing the segmentation process. The first option is to **Delete** *hidden points*, which removes any points which have been previously selected and are hidden.

The second option is *Confirm segmentation*, which separates the unwanted points from those to be kept in different layers.



Eliminating the layer of unwanted points: if you have selected **Confirm segmentation**, it is advisable to delete the layer of unwanted points. To do this, click on the layer that contains them and then right-click it. Select **Delete** from the drop-down menu.



Results of cleaning the point clouds: once the point cloud has been cleaned, you will see that the yellow edges of the box containing the point cloud fits much better than at the beginning.


Cleaning the point clouds is important if you want to obtain the best results.

Ele		Display Plugins																				68
P	🖬 💠 🖪	🗄 🖻 🗙	3 11	9 49 10	21 2	- M. 8	8 🕭	· *	4 🖉	• 11	L K	2.2	7 O	10	+	а.	2	R	1 -	Remo	ve filter	* S
	B Tree		8																			
/	🖯 <table-cell> 🏹 Toten</table-cell>	ply (/home/angell																				
÷.	😴 🖨 Tot	ern - Cloud.segme	n								-6											
14																						
т																						
×		Camera L	ink																			
÷,	roperties		8																			
Q.																						
	Property	State/Value	.11								100											
	CC Object Name	Totem - Cloud a	9 H.																			
1	Value	Totem - Cloud.s.	11								1000		- M									
	Show name (in	0	11								105											
	Colors	RGB										100										
		X: 77.3237	-									-										
	Box dimensions										2.0	0.0	40									
1		Z: 190.663																				
-	Box center	X: 0.722837 Y: -7.99427																				
	box center	1: -7.99427																		100		
-	onsole																					0
× .	[17:08:561[VBC) VBO(s) (re)initia	lized for	loud 'Toten	- Cloud (0.88 Mb	= 100	DOX of a	oints co	uld be	loaded)											-
		VBO(s) (rejinitia										In Local										

Processing the point cloud

In order to process a point cloud you will need to create the object normals:


Compute normals menu: the first step is to select the layer containing the point cloud which you want to compute the normals for.



Go to Edit > Normals > Compute.

Compute normals window: here you will need to adjust the orientation. It is recommend to use the –*Barycenter* orientation and to keep the default values for the rest.

Once you have adjusted the settings, click on *Apply*. The program will take a few seconds to compute the normals. Once it has finished click on the *Close* button.



HORUS

Reconstructing the point cloud with CloudCompare

Showing the normals: the normals visualisation is enabled by default. If not, you can do this by right-clicking on the layer that the normals have been computed for, and then click on *Toggle normals*. To hide them, click on the same tab again.

For an accurate reconstruction, the normals must be facing away from the piece, mean that, the object will be black (the colour of the normals). If the exterior of the object is not black but the interior is, this means that the normals have been computed backwards.

In the tests carried out -*Barycenter* is selected as the orientation parameter and the normals are always computed away from the object. However, if they have been computed backwards, they can be inverted by going to *Edit > Normals > Invert*.


			c	isudCompare v2.6.0 [64 b	its] - [3D View 1]					
File	Edit Tools	Display Pluging	3D Views Help							8.8
Ø	日 小 日	🔆 (म. 🗙	🕹 10 🐵 🖾 🖉 🖉 😥	88 🕭 🖌 🔶 🛲	IL K S Y	0 = +	11 2	K HH -	Remove filter	» S
2		ply (/home/angel	e default point size							
	- C - Tot	ers - Cloud segn Octree	Information (recursive)		0000					
+		Camera	Toggle Toggle visibility Toggle color							
H-	Properties		Toggle normals							
Q.	Property	State/Value	Toggle SF Toggle 3D name							
0	Name Visible	Totem - Cloud.	Delete							
9	Normals Show name (in	•	Add empty group							
1	Colors	RGB	Expand branch							
	Box dimensions	X: 77.3237 Y: 73.7606 Z: 190.663	Collapse branch			- 4				
-		X: 0.722837								
-	Console									1
			SateNormalOrientations] Barycenter: (2. Is) Timing: 19.01 s.	10379,-4.15918,95.4845	0					
			is) terming: 19.01 s. kized for cloud "Totem - Cloud segmente	ď (10.87 Mb = 100.00% c	f points could be loaded					

Reconstructing the object from the point cloud

From the normals generated in the previous section, you can proceed to reconstruct the object.

Reconstruction tool menu: you can access the point cloud reconstruction tool via *Plugins > Poison Surface Reconstruction*.

Click on it to open the tool window.



Reconstruction tool window: in this window you can modify the Octree Depth value

The recommended values are between 6 and 12 (if your computer is not very powerful the maximum recommended value is 11). It is advisable to keep the defaults for all other values.

As these variables are increased, the accuracy of the final model will also increase, however, the processing time will also be longer.

Once you have adjusted the value, click on **OK**. The processing time can range from several seconds to several minutes, depending on the specifications of the computer which is running the program.

It is not advisable to use a low spec computer for processing point clouds.

Poisson Surface	Reconstruction •
Octree depth	8
Advanced	
samples per node	1.00
full depth	5
point weight	4.00
Densty output density 	as SF
Density is useful to re mesh extents to fit as to the input point clo 'min displayed' value remaining part of the	s much as possible ud. Use the SF until the
Can	cel <u>O</u> K

Importing colours from the point cloud to the reconstruction: once the reconstruction process has finished, a window will appear asking if you want to import the colours of the point cloud to the reconstruction.


If you have scanned with texture, or without texture but you want to retain the colour of the point cloud, click on **Yes**. The process of importing the colour may last from a few seconds to a few minutes, depending on the number of points that the cloud has and the specifications of the computer running the process.

If you do not want to import the colour, click on No.

						laudCor	npare v2.6.	0 [64 bits] - [3D Vie	rw 1]							×
C Ele	Edit Tools	Display Plagins	3D View	s <u>H</u> elp													ER
Ø		6 D X	5 10	🐵 🖾 😣	1.21 10	88 4	A r.	4 🛲	A. K.	5. 7	0	÷ +	- E - E	2 14	88	* Remove filt	er » S
	DB Tree	nply (home/angel) tern - Cloud segne Octree	8]					
÷~ Q	Properties	State/Value				import	Poisson r			e some tim	ļ						
88	Name Visible Normals	Totem - Cloud.s.			~				No	Yes							
	Show name (in Colors	. C RGB															
	Box dimensions	Y: 73.7606 Z: 190.663 X: 0.722837															
	Console																0
	[17:15:14] [Pos	D] VBO(s) (rejinitia ssonRecon] Job sta ssonRecon] Job fini	ted (level i	5)			87 Mb = 10	0.00% of p	wints could	d be loaded]

Saving the results of the reconstruction

Save menu: to save the results of the reconstruction it is important to select the Mesh layer. Then click on *File > Save*.



Save window: save it STL format, select the location where you want to save it, then click on the *Save* button.


You should choose the *STL* format because all the slicing software programs used in 3D printing can open it correctly. If you want to export the file for other uses, you can select a different format.

	Save file	
iame:	\$en	
ave in folder:	Sangelin Scores Scares	Create
Places	Name	Size Modifi
Q Search	🕒 Dola.sti	41.7 MB 17.19
Recently Used		
angellm		
Desktop		
File System		
TI31071700A		
DATA		
Documents		
Music		
Pictures		
Videos		
Downloads		
+ -		STL mesh
		Cancel


Merging point clouds with CloudCompare

The point cloud may sometimes be incomplete, due to the geometry of the scanned object or the number of lasers used during the scanning process. The solution is to scan the object again by placing it in different position on the platform or by using another laser. Then merge the two point clouds together. To explain how this method works, we have used two point clouds, however, this process can be carried out with as many point clouds as you like - the procedure remains the same.

Open the ".ply" files of the point clouds from the two scanning processes.




Align tool: select the layers that you want to align and click to open the tool. The Align icon is located on the tool bar.



A window will then appear showing the "reference" layer (yellow) and the layer "to align" (red).

Click on *Swap*. The reference layer and the layer to align will have changed places.

Click on **OK** to continue aligning the layers.




Selecting point on the layer to be aligned: in this window the point clouds can be oriented to make it easier to align the points.

Then select at least four matching pairs of points on each of the point clouds to be aligned. Being overlapped, we recommend ticking the "Show reference cloud" box to hide it and facilitate selection of the points.

To select a point of the cloud, simply click on it. If you want to deselect a particular point, click on the button marked with an X, to the right of the point coordinates.

The points are accompanied by a letter and a number. Letter "A" indicates a point belonging to the layer to be aligned, and the number indicates the order that the points were selected in.



HORUS

Reconstructing the point cloud with CloudCompare


Selecting points on the reference layer: once the points have been selected on the layer to be aligned, select the corresponding points on the reference layer.

In order to select points on the reference layer, it is useful to hide the other layer, although you will most likely need to show from time to time in order to remember the location of the point on that layer.

The points must be selected in the same order, as the order of selection is very important. In order to obtain good results, very similar points must be selected in both layers.

As with the other layer, the selected points are accompanied by a letter and a number. Letter "R" indicates a point belonging to the layer to be aligned, and the number indicates the order that the points were selected in.


Once the points have been selected on both layers, click on Confirm.



Align info: a pop-up window will appear containing information on the cloud alignment process. Click on *OK* to continue.


		Align info		
8	Final RMS Transform			
	0.986	-0.166	0.033	-7.254
	0.165	0.986	0.012	25.176
	-0.035	-0.007	0.999	-0.829
	0.000	0.000	0.000	1.000
	Scale: fixe	d (1.0)		
	Refer to C	Console (F8)	for more de	tails
				ок

Viewing the results of alignment: simply by looking, you can see that the point cloud resulting from the alignment process is denser, which makes the results of the reconstruction more accurate.



Merging point clouds: the clouds are now aligned, but they have not yet been merged. To merge the clouds, you will need to select them and then click on: *Edit > Merge*.

The normals can now be computed and the object reconstructed, as explained earlier.




Printing the results of the reconstruction

There is one disadvantage when it comes to processing point clouds in CloudCompare: in general it does not close the objects. Taking the totem as an example, once the top and bottom have been reconstructed, they remain open and the object is hollow inside.


This can cause problems when printing the 3D model, as the program could recognise the object as a hollow cylinder and would print only the walls.

We will explain how to resolve this problem later, using the Cura slicing and printing software.

Running Cura: this is the main window of the Cura program. There is a menu at the top, a panel with four tabs on the left and a 3D viewfinder that occupies most of the window.



Opening a 3D model: to open a 3D model, click on File > Load model file...



Open model window: in this window, you can browse the directories and select the 3D model to be printed.

		Cura - 15.02.1		
file Tools Machine	Examt Helo	Open 3D model		
	n Desktop Scans			
 Imangeur 	Carls Desktop			
Places	Name			Modified ^
Q, Search	Totem.sti		41,7 143	17:21
Recently Used	[]] Bola.stl		41.7 MB	17:19
iii cura				
angelim				
Desktop				
3 File System				
3 TI31071700A				
DATA E				
Documents				
Music				
Pictures				
Videos				
Downloads				
+ -			All (*.sti;*.ooj;*.dae,*.amf;*.bmp;*.jpg;*.jpeg;*.png,*.	g.*.gcode)
			Cancel	Open
			Cancel	Op

Once you can selected the file, click on Open.

Visualisation of the model: once open, the 3D model will appear in the window. Right click and hold to change the orientation and use the mouse wheel to adjust the zoom.

From this view you can see that our 3D model is hollow.


ile Tools Machine Expe	it Help		Cura - 15.02	.1	
Basic Advanced Flugins	Start/End-G	Code			
Quality			🖆 🔛 🔛		1
Layer height (mm)	0.2		7 hours 3 minutes ALFS maker V2A germ		
Shell thickness (mm)	1.0		Consolitation of Solitation		
Enable retraction	· -				
rill					
Bottom/Top thickness (mm					
Fill Density (%)	20			500000000	
Speed and Temperate	ire				
Print speed (mm/s)	50				
Printing temperature (C)	215				
Bed temperature (C)	0				
Support					
Support type	Everywhere				
Platform adhesion type	None				
Filament					
Diameter (mm)	1.75				
Flow (X)	100.0				

Viewing the printing layers: occasionally, Cura will detect hollow objects and fill them automatically. If the reconstruction of the object has left points inside the model, it will not be filled automatically.

The best way to see if the model will to be printed correctly is by changing the view to *Layers* mode, where you will see how the layers will be printed by the printer.

HORUS

Reconstructing the point cloud with CloudCompare




Incorrect slicing: to check whether Cura has automatically filled the model, change the view to *Layers* mode.

The bar on the right indicates the number of layers in view. Slide the bar up or down to see more or less layers.

To check the filling of the object, ideally go to one of the in-between layers of the model. The program may take some time to process the layers. If the model is shown as hollow after the processing has finished, it has not been filled automatically.

On the other hand, if a mesh is shown inside the model, it has been filled automatically and you can now proceed to print it.

The image on the left shows a sliced model which has not been filled automatically by the program.



Expert configuration: to resolve the filling issue of the model, open the Expert config window.

To open this window, go to Expert > Open Expert Settings.

Under *Fix horrible*, only the *Combine everything (Type-A)* box is ticked by default, to fill the entire model you will need to tick *Combine everything (Type-B)*.

Then click on OK.




Once the printing file (GCode) has been generated, it is important to open the expert configuration again and reverse the changes that were made. Failing this, errors and unwanted fillings could occur next time you slice.

	Expert					
Retraction		Support	Support			
Minimum travel (mm)		Structure type	Grid ~			
Enable combing	All ~	Overhang angle for support (deg)	55			
Minimal extrusion before retracting (mm)	0.02	Fill amount (%)	20			
Z hop when retracting (mm)	0.0	Distance X/Y (mm)	0.7			
Skirt		Distance Z (mm)	0.2			
Line count	1	Black Magic				
Start distance (mm)	3.0	Spiralize the outer contour				
Minimal length (mm)	150.0	Only follow mesh surface	0			
Cool		Brim Brim line amount	20			
Fan full on at height (mm)	0.5		20			
Fan speed min (K)	100	Raft	5.0			
Fan speed max (%)	100	Extra margin (mm)	3.0			
Minimum speed (mm/s)	10	Line spacing (mm)	0.3			
Cool head lift		Base thickness (mm)				
Infill		Base line width (mm)	1.0			
Solid infill top	~	Interface thickness (mm)	0.27			
Solid infill bottom	15	Interface line width (mm)	0.4			
Infill overlap (%)	15	Airgap	0.0			
		First Layer Airgap	0.22			
		Surface layers	2			
		Surface layer thickness (mm)	0.27			
		Surface layer line width (mm)	0.4			
		Fix horrible				
		Combine everything (Type-A) Combine everything (Type-B) Keep open faces				
		Extensive stitching				

Correct slicing: to check that the changes make in *Expert config* have resolved the filling issue, as before, you will need to view one of the in-between layers again.

The image on the left shows the model perfectly filled and ready for printing.



Save menu: last of all, to save the printing file (GCode) click on File > Save GCode.

			Cura	- 15.02.1		×
File Tools Machine Exp	ert Help					
Load model file	Ctritt -G	Code	000			-
Save model	Ctrl+S					<u>.</u>
Reload platform	FS		4 lines 30 minutes			
Clear platform			4 bene 20 mbries 10.00 maar 60 gem			
Print	Ctrl+P					
Show slice engine log						
Open Profile						
Save Profile						
Load Profile from GCode.						
Reset Profile to default						733
Preferences	Ctrl+,			2		
Machine settings						500
Recent Model Files	>	v .			88 B	
Recent Profile Files	,	× .				
Guit	Ctri+Q					
Diameter (mm)	2.85					
Flow (X)	100.0					
Flow (X)	100.0					8

Save window: the save window will then appear. Via this window, you can browse the directory and save the file in the desired location.

Once you have entered the file name and selected the location click on *Save*.

ite Tools Machine Exper	e new					Save toolpath			
Basic Advanced Flugins	Start/E					Sare toopatr			
Quality		Name:	Tete	n gcode					
Layer height (mm)	0.2	Save in folder:	2	Documents	Ciclos & Horus	Pruebas Escaner	Pruebas Cloud Compare	> Create Folder	
Shell thickness (mm)	1.0								
Enable retraction		Places		Name				1	
Fill		Q Search							
Bottom/Top thickness (mm)	0.6	🕙 Recently Use	M						
Fill Density (X)	20	🏙 cura							
Speed and Temperatu	re	🔝 angetim							
Print speed (mm/s)	50	🔤 Desktop							
Printing temperature (C)	240	C File System							
Bed temperature (C)	70	TI31071700	A						
Support		DATA							
Support type	None	Documents							
Platform adhesion type	None	Pictures							
Filament		Wideos		1				I	
Diameter (mm)	2.85			_					
Flow (X)	100.0							Toolpath (*.gcode) \vee	
								Cancel Save	



For more information, please contact: support.3d.en@bq.com

www.bq.com diwo.bq.com